



Pocket Guide

Configure SF-OS to use LDAP server for authentication

Product: Sophos XG Firewall

Contents

Scenario	3
Prerequisites	
Configuration	
Step 1: Create the LDAP group (optional)	
Step 2: Configure LDAP authentication	5
Step 3: Select LDAP as Authentication Server	6
Results	6
Copyright Notice	7

Scenario

This guide describes how to integrate Sophos XG Firewall (SF-OS) with LDAP (Lightweight Directory Access Protocol) to authenticate users.

Prerequisites

- You must have read-write permissions on the SF-0S Admin Console for the relevant features.
- You will need the following LDAP parameters during the integration:
 - o LDAP server IP address and port
 - LDAP version
 - o LDAP administrator username and password (If Anonymous Login is disabled)
 - Authentication Attribute is used to perform user search. By default, LDAP uses UID attribute to identify user entries.
 - Group Name Attribute, Display Name Attribute, Email Address Attribute and Expire
 Date Attribute

PGAHM1011201601 Page 3 of 7

Configuration

Log in to the SF-OS Admin Console.

Step 1: Create the LDAP group (optional)


By default LDAP users are added to the Default group of SF-OS. If you do not want to add them to the Default group, create a new LDAP group in SF-OS. The group is synchronized with the LDAP server at the time of each user's first login.

- Go to Configure >
 Authentication >
 Groups and click Add.
- Set Group Type to
 Normal to log in using
 the client device; or to
 Clientless to perform
 access control through
 IP address.
- You can create, or choose the Policies.
- To override a user's group policy, create or choose Remote Access and Clientless policies.

Note: Remote Access: To deny SSL VPN access, select No Policy Applied.

 Login restriction allows access from any or specified nodes.


Click Save.



PGAHM1011201601 Page 4 of 7

Step 2: Configure LDAP authentication

- Go to Configure >
 Authentication > Servers
 and click Add.
- Set Server Type to LDAP Server.
- The default Port is based on the Connection Security that you select. Change the port number, if required.
- For Connection Security
 options SSL/TLS or
 STARTTLS, select Validate
 Server Certificate, if
 required.
- Client Certificate is set to the default certificate, change if required.
- Click Get Base DN to retrieve it from the LDAP directory.
- To use an attribute other than the default UID, enter the Authentication Attribute.



Note:

For Connection Security option Simple, username and password are communicated in plain text between SF-OS and LDAP.


Click Save.

PGAHM1011201601 Page 5 of 7

Step 3: Select LDAP as Authentication Server

- Go to Configure > Authentication > Services
- Within Firewall Authentication Methods, go to the Authentication Server List and select the LDAP Server you have configured in Step 2.
- In the Selected Authentication Server list, drag the selected LDAP server to the top. This LDAP server will act as the primary authentication server.

Click Apply.



Results

You have integrated SF-OS with LDAP. All users will be authenticated by this LDAP server.

PGAHM1011201601 Page 6 of 7

Copyright Notice

Copyright 2015-2016 Sophos Limited. All rights reserved.

Sophos is a registered trademark of Sophos Limited and Sophos Group. All other product and company names mentioned are trademarks or registered trademarks of their respective owners.

No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, photocopying, recording or otherwise unless you are either a valid licensee where the documentation can be reproduced in accordance with the license terms or you otherwise have the prior permission in writing of the copyright owner.

PGAHM1011201601 Page 7 of 7